


# Postscript settings for QuarkXpress 6


## 1. LAYOUT

Always include auto trim marks, offset 12pt.




## 2. SETUP

Use the **Acrobat Distiller** OR **Prinergy Refiner** PPD. Set paper width and height to 30mm larger than your document (ie allowing 15mm extra space all around). Ensure page positioning is centre. Always set orientation to Portrait.




## 3. OUTPUT

Settings as below. **NOTE:** If your document contains spot coloured TIFFs, use Device N, NOT As is, see 4.




## 4. OUTPUT (if using spot coloured TIFFs)




## 5. OPTIONS

Always select Full Resolution TIFF Output.



## 6. LAYERS


Set as required depending on layer use.



# Postscript settings for QuarkXpress 6 (continued)


## 7. BLEED

Set to 3mm.




## 9. PREVIEW

Check to be sure that the document fits properly.



## 8. OPI


Always turn OPI off.



**To save as postscript:** Click on the "Printer" button.

Ignore the Printer selected as this is irrelevant when saving postscript.

Select Output Options from the pop up menu, and set as shown below.



Save the postscript then run it through Distiller to create the PDF. Be sure to set up Acrobat Distiller as per the Finsbury instructions.